

## Industrial Automation Headquarters

**Delta Electronics, Inc.**  
Taoyuan Technology Center  
No.18, Xinglong Rd., Taoyuan District,  
Taoyuan City 33068, Taiwan  
TEL: 886-3-362-6301 / FAX: 886-3-371-6301

## Asia

**Delta Electronics (Shanghai) Co., Ltd.**  
No.182 Minyu Rd., Pudong Shanghai, P.R.C.  
Post code : 201209  
TEL: 86-21-6872-3988 / FAX: 86-21-6872-3996  
Customer Service: 400-820-9595

**Delta Electronics (Japan), Inc.**  
Tokyo Office  
Industrial Automation Sales Department  
2-1-14 Shibadaimon, Minato-ku  
Tokyo, Japan 105-0012  
TEL: 81-3-5733-1155 / FAX: 81-3-5733-1255

**Delta Electronics (Korea), Inc.**  
Seoul Office  
1511, 219, Gasan Digital 1-Ro., Geumcheon-gu,  
Seoul, 08501 South Korea  
TEL: 82-2-515-5305 / FAX: 82-2-515-5302

**Delta Energy Systems (Singapore) Pte Ltd.**  
4 Kaki Bukit Avenue 1, #05-04, Singapore 417939  
TEL: 65-6747-5155 / FAX: 65-6744-9228

**Delta Electronics (India) Pvt. Ltd.**  
Plot No.43, Sector 35, HSIIDC Gurgaon,  
PIN 122001, Haryana, India  
TEL: 91-124-4874900 / FAX : 91-124-4874945

**Delta Electronics (Thailand) PCL.**  
909 Soi 9, Moo 4, Bangpoo Industrial Estate (E.P.Z),  
Pattana 1 Rd., T.Phraksa, A.Muang,  
Samutprakarn 10280, Thailand  
TEL: 66-2709-2800 / FAX : 662-709-2827

**Delta Electronics (Australia) Pty Ltd.**  
Unit 20-21/45 Normanby Rd., Notting Hill Vic 3168, Australia  
TEL: 61-3-9543-3720

## Americas

**Delta Electronics (Americas) Ltd.**  
Raleigh Office  
P.O. Box 12173, 5101 Davis Drive,  
Research Triangle Park, NC 27709, U.S.A.  
TEL: 1-919-767-3813 / FAX: 1-919-767-3969

**Delta Greentech (Brasil) S/A**  
São Paulo Office  
Rua Itapeva, 26 – 3° Andar - Bela Vista  
CEP: 01332-000 – São Paulo – SP - Brasil  
TEL: 55-11-3530-8643 / 55-11-3530-8640

**Delta Electronics International Mexico S.A. de C.V.**  
Mexico Office  
Gustavo Baz No. 309 Edificio E PB 103  
Colonia La Loma, CP 54060  
Tlalnepantla, Estado de México  
TEL: 52-55-3603-9200

## EMEA

**Headquarters: Delta Electronics (Netherlands) B.V.**  
Sales: Sales.IA.EMEA@deltaww.com  
Marketing: Marketing.IA.EMEA@deltaww.com  
Technical Support: iatechnicalsupport@deltaww.com  
Customer Support: Customer-Support@deltaww.com  
Service: Service.IA.emea@deltaww.com  
TEL: +31(0)40 800 3900

**BENELUX: Delta Electronics (Netherlands) B.V.**  
De Witbogt 20, 5652 AG Eindhoven, The Netherlands  
Mail: Sales.IA.Benelux@deltaww.com  
TEL: +31(0)40 800 3900

**DACH: Delta Electronics (Netherlands) B.V.**  
Coesterweg 45, D-59494 Soest, Germany  
Mail: Sales.IA.DACH@deltaww.com TEL:  
+49(0)2921 987 0

**France: Delta Electronics (France) S.A.**  
ZI du bois Challand 2, 15 rue des Pyrénées,  
Lisses, 91090 Evry Cedex, France  
Mail: Sales.IA.FR@deltaww.com  
TEL: +33(0)1 69 77 82 60

**Iberia: Delta Electronics Solutions (Spain) S.L.U**  
Ctra. De Villaverde a Vallecas, 265 1º Dcha Ed.  
Hormigueras – P.I. de Vallecas 28031 Madrid  
TEL: +34(0)91 223 74 20

Carrer Llacuna 166, 08018 Barcelona, Spain  
Mail: Sales.IA.Iberia@deltaww.com

**Italy: Delta Electronics (Italy) S.r.l.**  
Via Meda 2–22060 Novedrate(CO)  
Piazza Grazioli 18 00186 Roma Italy Mail:  
Sales.IA.Italy@deltaww.com  
TEL: +39 039 8900365

**Russia: Delta Energy System LLC**  
Vereyskaya Plaza II, office 112 Vereyskaya str.  
17 121357 Moscow Russia  
Mail: Sales.IA.RU@deltaww.com  
TEL: +7 495 644 3240

**Turkey: Delta Greentech Elektronik San. Ltd. Sti. (Turkey)**  
Şerifali Mah. Hendem Cad. Kule Sok. No:16-A  
34775 Ümraniye – İstanbul  
Mail: Sales.IA.Turkey@deltaww.com  
TEL: + 90 216 499 9910

**GCC: Delta Energy Systems AG (Dubai BR)**  
P.O. Box 185668, Gate 7, 3rd Floor, Hamarain Centre  
Dubai, United Arab Emirates  
Mail: Sales.IA.MEA@deltaww.com  
TEL: +971(0)4 2690148

**Egypt + North Africa: Delta Electronics**  
Unit 318, 3rd Floor, Trivium Business Complex, North 90 street,  
New Cairo, Cairo, Egypt  
Mail: Sales.IA.MEA@deltaww.com

# Software Download Manual



## Software Download and Installation Manual

## Copyright notice

©Delta Electronics, Inc. All rights reserved.

All information contained in this user manual is the exclusive property of Delta Electronics Inc. (hereinafter referred to as "Delta ") and is protected by copyright law and all other laws. Delta retains the exclusive rights of this user manual in accordance with the copyright law and all other laws. No parts in this manual can be reproduced, transmitted, transcribed, translated, or used in any other ways without the prior consent of Delta.

## Limitation of Liability

The contents of this user manual are only for the use of the DIAInstaller manufactured by Delta. Except as defined in special mandatory laws, Delta provides this user manual “as is” and does not offer any kind of warranty through this user manual for using the product, either express or implied, including but not limited to the following:

- (i) this product will meet your needs or expectations;
- (ii) the information contained in the product is current and correct;
- (iii) the product does not infringe any rights of any other person. User shall bear their own risk to use this product.

In no event shall Delta, its subsidiaries, affiliates, managers, employees, agents, partners and licensors be liable for any direct, indirect, incidental, special, derivative or consequential damages (including but not limited to the damages for loss of profits, goodwill, use or other intangible losses) unless the laws contains special mandatory provisions to the contrary.

Delta reserves the right to make changes to the user manual and the products described in the user manual without prior notice and afterwards.

---

---

## Related Documents

<b>Document Name</b>	<b>Document ID</b>
DIADesigner User Manual	<b>DIAS-Manual-0003-EN</b>
DIAScreen User Manual	<b>DIAS-Manual-0004-EN</b>
DIADesigner-AX User manual	<b>DIAS-Manual-0014-EN</b>
DIASelector User Manual	<b>DIAS-Manual-0002-EN</b>
COMMGR User Manual	<b>DIAS-Manual-0006-EN</b>

---

---

## Revision History

Version	Issue Date	Revision
1 <sup>st</sup>	2020/12/08	The first version release.

---

## Table of Contents

Chapter 1: Overview.....	1
1.1 DIAStudio Integrated Engineering Software.....	2
1.1.1 Key Software .....	2
1.2 DIAInstaller Introduction.....	3
Chapter 2: Getting Started .....	4
2.1 System Requirement.....	5
Chapter 3: Installation and Uninstallation .....	6
3.1 Introduction .....	7
3.2 Installing DIAInstaller .....	7
3.3 Uninstalling DIAInstaller .....	14
Chapter 4: User Interface .....	16
4.1 UI Introduction.....	17
4.2 DIAInstaller Functions .....	18
4.2.1 Software List Functions .....	19
4.2.2 Option .....	20
Chapter 5: Software List Operation .....	22
5.1 Introduction .....	23
5.2 Downloading and Installing Software Products .....	23
5.3 Uninstalling Software Products .....	26
5.4 Update Software .....	27
5.4.1 Check for Updates Manually.....	27
5.4.2 Check for Update Automatically.....	28
5.4.3 Update Software (When there is a new version of software available).....	30
5.4.4 Software update (when there is a new patch).....	31

---

---

## Chapter 1: Overview

---

## 1.1 DIAStudio Integrated Engineering Software

The DIAStudio is an all-in-one integrated engineering platform, on which users can efficiently develop machinery systems, from product selection, programming, to exporting.

It simplifies the process, and helps to save time and cost for building machinery systems.



Figure 1 - 1: DIAStudio Features

### 1.1.1 Key Software

The DIAStudio comprises of 5 key software:

- **DIASelector:** Quick, easy, smart selection tool.
- **DIADesigner:** Integrated development & engineering software.
- **DIAScreen:** Intuitive visualization software.
- **DIAInstaller:** System installation & update management
- **COMMGR:** Communication management
- **DIADesigner-AX:** Motion development and engineering software

The DIAStudio supports efficient and flexible data transmission between software. It also facilitates for tag sharing between software.

## 1.2 DIAInstaller Introduction

The DIAInstaller is a software installer, which assists user to download, install & un-install, update DIAStudio software applications. User can download, install, and update products such as DIASelector, DIADesigner, DIADesigner-AX DIAScreen, and COMMGR.

The key features of DIAInstaller are:

- Install and uninstall the products.
- Check for the latest product updates.
  - Check Manually.
  - Set an automatic check for update of products at required frequency.
- Set the language. Supported languages are English, Simplified Chinese and Traditional Chinese.
- View the Copyright notice and current version of DIAInstaller.
- Download the products.
- Includes patch function to update specific components.



---

## Chapter 2: Getting Started

---

## 2.1 System Requirement

	<b>System Requirement</b>
Operating System	Windows 7 / 8.1 / 10 32/64 bits
CPU	Intel Celeron 540 1.8GHz (min.) · Intel Core i5 M520 2.4 GHz
Memory	2GB or above (recommend to use 4GB or more)
Hard Disk Drive	10GB or more
Monitor	Resolution: 1024 x 768 Pixels, 1920 x 1080 Pixels
Keyboard/Mouse	General Keyboard Mouse or Windows compatible device
Ethernet	Need network connection when down or update
Software	Need to install Microsoft.Net Framework 4.6.2

---

## Chapter 3: Installation and Uninstallation

---

## 3.1 Introduction

The installation and uninstallation procedures are provided in the following sections.

### 3.2 Installing DIAInstaller

### 3.3 Uninstalling DIAInstaller

## 3.2 Installing DIAInstaller

### Pre-requisites:

Ensure that the target computer follows the minimum criteria mentioned in 2.1 System Requirement, and can be connected to Ethernet.

To download the software, DIAStudio registration is mandatory.

Follow the steps to install software:

1. Open the following website through browser:


<https://diastudio.deltaww.com/>

2. Click on **DIAStudio** > **Download** menu or Go to the Download field of **Information** and click **Software** to open the download page. If you have not logged in, you will first enter the login page.



**Figure 3 - 1: DIAStudio Website**

3. Enter DIAStudio account information and sign in.




The image shows a sign-in form for Delta. At the top is the Delta logo, which consists of a blue triangle with a white circle inside, followed by the word "DELTA" in blue. Below the logo is the text "Sign in with your existing account". There are two input fields: "Email Address" and "Password". To the right of the "Password" field is a link that says "Forgot your password?". Below the input fields is a blue button with the text "Sign in". At the bottom of the form is a link that says "Don't have an account? Sign up now".

**Figure 3 - 2: Sign In**





4. Select the latest version of DIAStudio in the **Software Name**, and click the



Zip file in the **File** field to download it.




The image shows a screenshot of a website's software list. The table has five columns: Software Name, Description, OS, Issue Date, and File. The first row is highlighted in grey. A red box is drawn around the 'File' icon in the first row, and a blue arrow points to it from the right. A circular icon with a blue and white gradient is also visible on the right side of the table.

Software Name	Description	OS	Issue Date	File
DIAStudio V0.5 (Early Access!)	DIAStudio Software download and Installation Tool	Windows 7 / 8.1 / 10 / Server 2012 R2 32/64 bit	2020/09/11	
DIAStudio for DIADesigner-AX Beta V0.4 (Early Access!)	DIAStudio Software download and Installation Tool	Windows 7 / 8.1 / 10 32/64 bit	2020/07/30	
DIAStudio V0.4 (Early Access!)	DIAStudio Software download and Installation Tool	Windows 7 / 8.1 / 10 / Server 2012 R2 32/64 bit	2020/05/06	
DIASelector App V0.5 (Early Access!)	DIASelector Mobile App	Android Lollipop (5.0) and above	2020/09/11	


**Figure 3 - 3: DIAStudio Website**

5. Once the download is complete, double-click **DIAInstaller.exe** in download folder and then start to install it.




**Figure 3 - 4: Installation file**

6. Select the language, and then click on **OK** button.



**Figure 3 - 5: Select Language**


7. The operating system will ask for additional installation of Microsoft components. Please make sure that Microsoft .Net Framework 4.6.2 or above is installed. If not, user need to install it. Click on **Install** button to continue.



**Figure 3 - 6: Install**

**NOTE:** Please check if Microsoft .Net Framework 4.6.2 or version above is installed in system, or it will install extra Microsoft package according to user's system.

8. After installing extra packages, click on **Next** button to continue installation.



---


**Figure 3 - 7: InstallShield Wizard**

9. Read the Software License Statement carefully, if there is no further question, then, please select **I accept the terms in the license agreement** option and click on **Next** button. Else, please contact Delta Electronics Inc.

**Figure 3 - 8: DIAInstaller Software License Statement**


10. Confirm install destination folder, or click on **Change** button to set custom destination folder, and then click on **Next** button to continue.





**Figure 3 - 9: DIAInstaller Destination Folder Setting**

11. If there is any setting need to be reset, click on **Back** button when needed. Otherwise, click on **Install** button to start installation.



**Figure 3 - 10: Copying files to Destination**

12. Click on **Finish** button to end the installation and DIAInstaller launches automatically once the installation is complete.




Figure 3 - 11: Installation Complete

### 3.3 Uninstalling DIAInstaller

Follow the steps to uninstall DIAInstaller:

1. Open **Control Panel**, select DIAInstaller in **Programs > Uninstall a program**, and then click **Uninstall** button.




Figure 3 - 12: Uninstall DIAInstaller in Programs and Features

2. Click on **Yes** button to uninstall DIAInstaller.



**Figure 3 - 13: Confirm to Uninstall DIAInstaller**

**Result:** DIAInstaller will be uninstalled after system process is complete.

**NOTE:** *Uninstallation of DIAInstaller will not uninstall any of the DIAStudio (DIASelector, DIADesigner, DIADesigner-AX, COMMGR, DIAScreen) software products which are already installed. But, user will not be able to update any of the DIAStudio products.*

---

## Chapter 4: User Interface

## 4.1 UI Introduction

The DIAInstaller screen contains three blocks.

- 1 Language Switch and Login Function.
- 2 Function Option.
- 3 Function Screen Operation.





Figure 4 - 1: DIAInstaller Interface





Click the current language from block 1 to switch the language. Currently, Traditional Chinese, Simplified Chinese and English are supported, as shown in the figure below.



**Figure 4 - 2: Switch Language**


## 4.2 DIAInstaller Functions

The DIAInstaller application includes Software Status ([4.2.1 Software List Functions](#)), Option ([4.2.2 Option](#)), About, and Language Setting functions. The functions in the DIAInstaller are described in the following table.

Function	Description
Software List 	User can download, install/uninstall, and update DIAStudio related software products, including DIASelector, DIADesigner, DIASceen, DIADesigner-AX and COMMGR via Software List function.
Option 	User can do settings using this option, such as setting update frequency, download path and check for update immediately.
Software Manual 	Click to open the DIAInstaller Software Manual
About 	User can view the Copyright notice and current version of DIAInstaller.

### 4.2.1 Software List Functions

The default screen of DIAInstaller is the Software List, which displays the supported product name, version, size, download/update, progress, installation/uninstallation, and set installation path. After logging in, user can download ,install and update the products whenever they need it. Please refer to [Chapter 5: Software](#) for related software list operations.



**Figure 4 - 3: Software List**

Functions in the software list are described in the table below:


Features	Description
Product Name	Name of DIAStudio software product.
Current Version	Latest version of corresponding product.
Size	Installation file size of corresponding product.
Download	The user can operate the product through the download icon.
Schedule	It shows the progress of downloading, installing, updating, download speed, estimated time left etc.



Features	Description
Install/uninstall	Users can perform corresponding operations on the product through the install/uninstall button.
Check for Updates	Users can check whether there is an updated version on the host.
Download All	Users can download all the software at once.

### 4.2.2 Option

The Option page is as shown in the following figure:



**Figure 4 - 4: Option Tab**

The Option functions are described in the following table:

Features	Description
Download Path	Shows current download path, which can be changed through the <b>Browse</b> button on the right.
Limit download speed to	You can set the total rate of the download limit. User can check to change the limit, by default it is unchecked.
Alert when the download target directory disk space is not enough	Check this item, the target disk of the download path, the minimum disk space is less than the set space size, and a warning will pop up during download.
Minimum disk space	Set to limit the minimum disk space remaining on the target disk.
Enable DIAInstaller to delete executable file after an application is installed (including update installation)	It deletes the executable files after an application is installed.
Application check for updates when DIAInstaller is opened	If this setting is enabled, when the software displays the screen, it will automatically check for updates.
Check for update automatically	The automatic update cycle can be set. (Daily).By default, this is updated on daily basis.
Display the new version notification window of this software	Displays the new version notification.
Check for Update Frequency	Users can check whether there is an updated version on the host.
Check for updates	User can check for any available update.
Cancel	Cancel this changed setting.
Apply Settings	Apply the modified settings after modification

---

## Chapter 5: Software List Operation

## 5.1 Introduction

User can download, install ([5.2 Downloading and Installing Software Products](#)), uninstall ([5.3 Uninstalling Software Products](#)), and update ([5.4 Update Software](#)) softwares in Software List page.

## 5.2 Downloading and Installing Software Products

Follow the steps below to install software:

1. Sign in to download a software.




Figure 5 - 1: Sign in Page

2. Select the product to download and click on **Download** button.




Figure 5 - 2: Download Software

**Result:** The download percentage is shown in progress.




Figure 5 - 3: Download Software Progress

3. After the software is downloaded, click the **Install** button to pop up the installation file of each installer and start the installation.

DIAStudio							
	Product Name	Issue Date	Version	Current Vers...	Size		
	DIADesigner	2020/12	1.0		1.4 GB	Downloaded	Install
	DIASelector	2020/11	0.5.01		777.2 MB	Installed	Uninstall
	DIAScreen	2020/11	1.0	1.0.0	1.8 GB	Installed	Uninstall
	COMMGR	2020/12	2.0	1.4.0	234.5 MB	Download Update	Uninstall
	DIADesigner-AX	2020/11	1.0.0	0.5.0	1.6 GB	Download Update	Uninstall


**Figure 5 - 4: Install Software**

**NOTE:** Only one installation process is allowed at the same time. Other install/uninstall button will be greyed out when a product is processing installation/uninstallation.








DIAStudio							
	Product Name	Issue Date	Version	Current Vers...	Size		
	DIADesigner	2020/12	1.0		1.4 GB	Downloaded	Install
	DIASelector	2020/11	0.5.01		777.2 MB	Installed	Uninstall
	DIAScreen	2020/11	1.0	1.0.0	1.8 GB	Installed	Uninstall
	COMMGR	2020/12	2.0	1.4.0	234.5 MB	Download Update	Uninstall
	DIADesigner-AX	2020/11	1.0.0	0.5.0	1.6 GB	Download Update	Uninstall

**Figure 5 - 5: Software Installation**

- After the installation is complete, window displays as **Uninstall**.



The screenshot shows the DIAStudio interface with a table of installed software. The 'Uninstall' button for 'DIADesigner' is highlighted with a red box.


DIAStudio							
	Product Name	Issue Date	Version	Current Vers...	Size		
i	DIADesigner	2020/12	1.0	1.0.0	1.4 GB	Installed	 Uninstall
i	DIASelector	2020/11	0.5.01		777.2 MB	Installed	 Uninstall
i	DIAScreen	2020/11	1.0	1.0.0	1.8 GB	Installed	 Uninstall
💡	COMMGR	2020/12	2.0	1.4.0	234.5 MB	 Download Update	 Uninstall
💡	DIADesigner-AX	2020/11	1.0.0	0.5.0	1.6 GB	 Download Update	 Uninstall

**Figure 5 - 6: Uninstall**








### 5.3 Uninstalling Software Products

Follow the steps to uninstall software:

1. Open DIAInstaller and click on **Uninstall** button on product to be uninstalled.

















The screenshot shows the DIAStudio interface with a table of installed software. The 'Uninstall' button for 'DIADesigner' is highlighted with a red box.

DIAStudio							
	Product Name	Issue Date	Version	Current Vers...	Size		
i	DIADesigner	2020/12	1.0	1.0.0	1.4 GB	Installed	 Uninstall
i	DIASelector	2020/11	0.5.01		777.2 MB	Installed	 Uninstall
i	DIAScreen	2020/11	1.0	1.0.0	1.8 GB	Installed	 Uninstall
💡	COMMGR	2020/12	2.0	1.4.0	234.5 MB	 Download Update	 Uninstall
💡	DIADesigner-AX	2020/11	1.0.0	0.5.0	1.6 GB	 Download Update	 Uninstall

**Figure 5 - 7: Uninstall Software**

2. The uninstall package of the software will pop up. After uninstalling, the status of the software will change to **Install**.

DIAStudio							
	Product Name	Issue Date	Version	Current Vers...	Size		
	DIADesigner	2020/12	1.0		1.4 GB	Downloaded	 Install
	DIASelector	2020/11	0.5.01		777.2 MB	Installed	 Uninstall
	DIAScreen	2020/11	1.0	1.0.0	1.8 GB	Installed	 Uninstall
	COMMGR	2020/12	2.0 	1.4.0	234.5 MB	 Download Update	 Uninstall
	DIADesigner-AX	2020/11	1.0.0 	0.5.0	1.6 GB	 Download Update	 Uninstall

**Figure 5 - 8: Software Uninstall Complete**


## 5.4 Update Software

This function allows user to check for updates manually or automatically, and update the software products in DIAInstaller.

### 5.4.1 Check for Updates Manually

Switch the function page to **Option**, and click on **Check for Updates** button. The system will check for any updates for all products.





**Figure 5 - 9: Check for Updates Manually**

### 5.4.2 Check for update automatically

A check for updates will be performed every time the computer is restarted; you can also set the automatic update frequency during the computer's turn on,

Follow the steps to check for updates automatically:

1. Select **Check for update automatically** and Select **Check for Update Frequency**. The default update frequency is daily.




Figure 5 - 10: Setting Automatic Check for Updates

2. Click on **Apply Settings** to change the settings.





Figure 5 - 11: Apply Option Setting

**Result:** System will check for update automatically according to user's setting.

### 5.4.3 Update Software (When there is a new version of software available)

Follow the steps to update a software:

1. Open the software list. If there is a new version of the installed software available, the new version icon will be displayed .





DIAStudio							
	Product Name	Issue Date	Version	Current Vers...	Size		
	DIADesigner	2020/12	1.0		1.4 GB	Downloaded	 Install
	DIASelector	2020/11	0.5.01		777.2 MB	Installed	 Uninstall
	DIAScreen	2020/11	1.0	1.0.0	1.8 GB	Installed	 Uninstall
	COMMGR	2020/12	2.0 	1.4.0	234.5 MB	 Download Update	 Uninstall
	DIADesigner-AX	2020/11	1.0.0 	0.5.0	1.6 GB	 Download Update	 Uninstall

Figure 5 - 12: Update Software Information

2. Click on **Download Update**, to start downloading the latest update.


















DIAStudio							
	Product Name	Issue Date	Version	Current Vers...	Size		
	DIADesigner	2020/12	1.0		1.4 GB	Downloaded	 Install
	DIASelector	2020/11	0.5.01		777.2 MB	Installed	 Uninstall
	DIAScreen	2020/11	1.0	1.0.0	1.8 GB	Installed	 Uninstall
	COMMGR	2020/12	2.0 	1.4.0	234.5 MB	 Download Update	 Uninstall
	DIADesigner-AX	2020/11	1.0.0 	0.5.0	1.6 GB	 Download Update	 Uninstall

Figure 5 - 13: Download Update

3. After download is complete, click on **Update Installation** button to update the product.



DIAStudio							
	Product Name	Issue Date	Version	Current Vers...	Size		
i	DIADesigner	2020/12	1.0		1.4 GB	Downloaded	Install
i	DIASelector	2020/11	0.5.01		777.2 MB	Installed	Uninstall
i	DIAScreen	2020/11	1.0	1.0.0	1.8 GB	Installed	Uninstall
💡	COMMGR	2020/12	2.0	1.4.0	234.5 MB	Update Installation	Uninstall
💡	DIADesigner-AX	2020/11	1.0.0	0.5.0	1.6 GB	Download Update	Uninstall

**Figure 5 - 14: Update Software**

**Result:** After installation, the status will display installed.

#### 5.4.4 Software update (when there is a new patch)


Open the software list. If there is a new patch for the installed software, the patch icon will be displayed at the back.

Follow the steps to update the software:

1. Click on **Download Patch**.

**Result:** Once the download is complete, it displays as Install patch.

2. Click on **Install Patch** to install the patch file.
3. After the installation is complete, user can see the version changes.



**Figure 5 - 15: Install Patch File**

**Remarks:**

**5.4.3 Update Software** (When there is a new version of software available)

introduces software updates when new versions of software are available; **5.4.4**

**Software update** (when there is a new patch) introduces software updates when new patches are available. The differences between the two are as follows:

- Software update when there is a new version of the software: When a new version of the software is released, user can choose to reinstall the new version to use the new features of the new version, but the entire installation process will take a long time.
- Software update when there is a new patch: When the current software version has major updates or corrections, user can choose to install patches to update some components, which saves time.